

Popular input formats & Applications

DOC, RTF, XML,	- Office-Word
HTM, HTML	- Office-Word or Netscape 4.6
XLS, CSV,	- Excel Viewer
PPT, PPS	- MS Office - Powerpoint
PDF,	- Adobe Reader
WRI,	- Windows WordPad
TXT, LOG, INI, INF, BAT,	- Windows NotePad
CPP, C, H, BAS, ASP, CXX, HXX	- Windows NotePad
PS, EPS,	- GSView
BMP, PCX, JPG, JPEG, JPE, GIF,	- Windows Imaging
TIF, TIFF, XIF, DCX	- Windows Imaging
DFT,	- Solid Edge Smart Viewer
DWG, DXF, DWF,	- Volo View Express 2

"Printto" Settings

Setup at: **Explorer | Tools | Folder Options | File Types | <Doc Format> | Advanced | Printto**

Basic formats: (Windows/Office/AcroReader)

BMP/GIF/JPG/PCX/TIF - "Printto" -> "xxx\KodakPrv.exe" /pt "%1" "%2" "%3" "%4"
DOC/HTM/HTML - MS Word, Printto -> "xxx\WINWORD.EXE" /n /dde %1 ...
HTM/HTML - MS Word, Printto -> "xxx\WINWORD.EXE" /n /dde %1 ...
Netscape 4.x, <http://download.cnet.com/downloads/0-3364665-100-7980579.html?tag=st.dl.10001-103-1.lst-7-1.7980579>
RTF - "xxx\Wordpad.exe" /p "%1"
TXT - "Printto" -> "xxx\notepad.exe" /pt "%1" "%2" "%3" "%4"
PPT - "xxx\POWERPNT.EXE" /p "%1"
XLS - Microsoft Excel Viewer 97/2000,
<http://office.microsoft.com/downloads/2000/xlviewer.aspx>
"Printto" -> "xxx\XLVIEW.EXE" /e "%1"
PDF - "Printto" -> "xxx\AcroRd32.exe" /t "%1" "%2" "%3" "%4"

Extended formats:

PS - GhostScrip & GSView, run once, no need to register.
DFT - Solid Edge Smart Viewer (<http://www.solid-edge.com/software/Smartview/smartview.htm>). Printto -> /p "%1"
DWG/DXF/DWF - Volo View Express, <http://www3.autodesk.com/adsk/index/0,,837403-123112,00.html>. Printto -> /p "%1"

Supported output formats

TIFF Group 3
TIFF Group 3 (2D)
TIFF Group 4
TIFF Pack Bits
Adobe PDF non-searchable
Intel DCX
ZSoft PCX

